

# DOWNLOAD eBooks FROM OVERDRIVE TO NOOK

1. Go to [www.killinglypubliclibrary.org](http://www.killinglypubliclibrary.org) / click “Audiobooks & eBooks” link (on left)

NOTE: YOU WILL ONLY NEED TO DO STEPS 2, 3, AND 4 ONCE. AFTER YOU HAVE PERFORMED THESE STEPS, YOU MAY PROCEED DIRECTLY TO STEP 5.

2. Download/install Adobe Digital Editions: [www.adobe.com/products/digitaleditions/](http://www.adobe.com/products/digitaleditions/)
3. Activate Adobe Digital Editions (will be prompted to do this after installation)
4. Authorize your computer using an Adobe ID. If you do not already have an Adobe ID, you will be prompted to set one up. Or you can visit: <https://www.adobe.com/cfusion/membership/index.cfm> to set one up. (This allows you to download and transfer titles to up to six computers and devices activated with the same Adobe ID.)

- 
5. Browse/search the Bibliomation OverDrive catalog for eBooks: <http://bibliomation.lib.overdrive.com>

6. Ensure you select the Adobe EPUB eBook option, and click “Add to My List”  
(You may also “Place a Hold” – you will be notified via email when the title is available)

7. If you are finished browsing/adding, click “Proceed to Checkout”

8. Select Killingly Public Library (or your participating hometown library)

9. Enter your KPL card number (barcode number), click “sign in”

10. Select lending period (14 or 21 days), and “confirm checkout”

11. Click “Download”

12. Select “Open with Adobe Digital Editions” option, and click “OK”  
(will download the book to Adobe Digital Editions software on your computer)

Transfer the title to your eReader device:

13. Plug the device into your computer using the appropriate USB cable

14. In Adobe Digital Editions, select “Library View” icon in the upper left corner of screen

15. Click/drag the title you just downloaded (visible on right) to your device (visible on left)

16. Disconnect the device and enjoy!

NOTE: Borrowed titles automatically expire at the end of the designated loan period. If you wish to return an item early, you do so from your Adobe Digital Editions. Ensure your device is plugged in to your computer. In the space showing the cover of the book, in the upper left corner, click the down arrow and select “Return Borrowed Item” from the list. It will disappear from your device and from your Adobe Digital Editions.

## **De-authorizing/re-authorizing Adobe Digital Editions on your computer and your reader**

### **Create an Adobe ID:** <https://www.adobe.com/cfusion/membership/index.cfm>

You may want to write down the email address and password you use.

If you are authorizing your Nook, use the same email address you used to register your Nook.

### **De-authorize your reader**

1. Plug your reader into your computer with the USB cable
2. Open Adobe Digital Editions
3. Make sure you can see your reader displayed at the bottom of the left on the left-hand side of the screen
4. Press <CTRL>+<SHIFT>+<E>
5. Select your reader from the drop-down list and then click Deauthorize
6. Unplug your reader from the computer

### **De-authorize your computer**

1. Open Adobe Digital Editions
2. Press <CTRL>+<SHIFT>+<D>
  - o De-authorize Computer box will appear and say, "Are you sure you want to de-authorize this computer? If you have protected items in your Digital Editions library, they may no longer be readable."
  - o Select De-authorize
  - o After selecting "De-authorize" a message will appear stating "Your computer was successfully de-authorized. Restarting Adobe Editions will require you to reactivate your computer."
  - o Click on "Quit"
3. Adobe Editions will close.

### **Re-authorize your computer**

1. Open Adobe Digital Editions
2. The Setup Assistant will appear, click "Continue" and then authorize/activate the computer with a new Adobe ID and password (that you created in the first step).
3. Close Adobe Digital Editions

### **Re-authorize your reader**

1. Plug your reader into your computer
2. \*If you are using a NOOK, be sure to delete the file called .adobe digital editions from your NOOK (using your computer) before continuing.\*
3. Open Adobe Digital Editions
4. Adobe Digital Editions should detect your device and offer to authorize it with your Adobe ID.